

Switcher



WORLDWIDE TECHNICAL BULLETINS FOR BROADCAST AND PROFESSIONAL PRODUCTS

Broadcast Products Technical Bulletin 20-2003-125

DATE: June 9, 2003

SUBJECT: SOFTWARE UPGRADE-VERSION 5.25

MODEL: BZS-7050A BZS-7060A DVS-7250A

-7250A

SERIAL NO: ALL

DESCRIPTION

Software version 5.25 is now available.

PARTS REQUIRED

Part No.	Description	Qty.
DS7060A15	DVS-7250A, BZS-7060A Software V5.25	1

ORDERING INFORMATION

To order upgrades, contact:

Sony SOFTWAREPLUS® Center

- Fax: 816-880-6854
- Call: 800-538-7550 → Option 5
- Mail: Sony SOFTWAREPLUS® Center

8281 NW 107th Terrace

Kansas City, MO 64153

Customers outside the United States: *Please order parts from your usual supplier.*

PROGRAM IMPROVEMENTS

Problems Corrected

- When pressing Proc Ctrl 2 with DME setup after choosing DME 1/2, the panel hung up.
- In KF, when Effect duration is set to "0," and Next KF/Prev KF was switched at a high speed, the switchers were all cleared.
- In a system with a redundant power supply, an abnormal power supply message was displayed. The algorithm to detect a momentary load change has been changed so that the message is displayed only when a continuous abnormality occurs.
- When issuing the duration attribute protocol from the axial editor to the DVS, the DVS processor was reset.
- When the Orthg button was selected in DME Ctrl, the Wipe Position Y parameter on the EL panel did not work in the downward direction.
- After copying between DME register channels from the switcher panel, the status display of No. 99 was the same as that of No. 98.

SWEM01-028

- When the DME was controlled from a switcher panel, powerup caused DME delegation in systems consisting of several DMEs.
- In the Disk menu, when the Effect register of the DME was called with the Shot Box function and the Run button was pressed, Effect was not executed.

Broadcast Professional Products Asia + Sony Australia + Broadcast Professional Products Europe + Sony Canada Ltd. + Sony Electronics Inc. USA + Sony Broadcast and Professional Latin America