

Ohio (Small Format Remote IO box) Programming & Configuration Information

Ohio M Ohio Fi	t Ohio Specification (as of 12/8/2010): ain app V1.32 (Ohio_MainApp.bin) rmware V3.02 (chip.rbf) 1 (main card within a OHIO unit) – Firmware V1.2 (SU5611_1v2.pof, programmed on board using Quartus)
EG533: Alpha 2	nder of the system needs to be (as of 12/8/2010): 2-2 Hydra interface box 3.0Z 2.8a: Control.bin//_, Rack.bin//_, Frontend.jar/_/_ 28: Control.bin//_, Rack.bin//_, Frontend.jar/_/_
HyperT	Terminal ferminal can be used to set IP & MAC addresses, to program the box software (Ohio_MainApp.bin), and to n core firmware (chip.rbf). The Hydra remotes utility command set is currently not compatible with Ohio units.
5	are the HyperTerminal connection with the Calrec default values: Serial port, 115200 Bps, 8 data bits, parity = none, stop bits = 1, flow control = none. "echo typed characters locally" is selected from File>Properties>Settings>ASCII setup
	erminal example – Normal boot messaging:
*	**************************************
S I I U	Setting primary IP address 192.168.0.50 Setting secondary IP address 192.168.0.150 Local MAC address 1: 0-d-7-7-0-5e Local MAC address 2: 0-d-7-7-0-5f Jdp connect: Found free udp descriptor 0 Connection made to protocol port 69, physical port 0 Jdp connect: Found free udp descriptor 1 Connection made to protocol port 69, physical port 1
*	*******************
*	CHEREE NODIO ETD
I F F F F I I U	System started initialising ownership Program mac 0 0x7 index 0 Program mac 1 0x0 index 0 Program mac 2 0x5e index 0 Program mac 0 0x7 index 1 Program mac 0 0x7 index 1 Program mac 0 0x6 index 1 Program mac 2 0x5f index 1 Program mac 2 0x5f index 1 Device open: GBit driverOuild date: Mar 7 2007 Build time: 09:50:11 Device open: GBit driver1 Udp connect: Found free udp descriptor 2 Connection made to protocol port 2000, physical port 0 Udp connect: Found free udp descriptor 3 Connection made to protocol port 2000, physical port 1 Sending boot up command

Original Calrec file location: S:\Custsupp\Guidance\Ohio\Ohio prog.doc
New SCI file location: Support:SW REVS:Hydra:OHIO prog v4.doc
Last printed 03/02/2014 11:51:00



Setting IP & MAC address

Using HyperTerminal with Calrec default settings, connected to the box via RS232 whilst box running main application (box has booted, not held in bootloader):

Type i <enter> to readback the current MAC & IP addresses for the box

To change ONLY the IP address enter: **Ipw A B C** (for port 1 only) $A = 1^{st}$ Octet, $B = 2^{nd}$ Octet, $C = 3^{rd}$ Octet

Eg. To program a box as IP Addr = 192.168.2.xxx

Enter: ipw 192 168 2 <enter>

To change BOTH the MAC AND the IP enter:
adr <MAC4> <MAC5> <MAC6> <IPbyte1> <IPbyte2> <IPbyte3>
(for port 1 only)

The full command above has to be entered, ie if only changing MAC, IP still needs to be entered and vice versa. A space should be entered between adr & the first value, and between subsequent values. No "."'s should be entered. Port 1 IP byte 4 is set by DIP switches on the rear of the unit.

Port 2 IP bytes 1 to 3 are automatically set the same as port 1 IP bytes 1 to 3.

Port 2 IP byte 4 is automatically set as port 1 IP byte 4 + 100

MAC addresses are split into groups of 2 digits. The first 3 pairs are automatically set as 00 0D 07. If the first of the two in a pair is a 0, this is omitted. ie for 04, enter / read 4. Port 2 MAC is automatically set as Port 1 MAC + 1

Eg, to program a box as MAC1 = 00 0D 07 00 04 4C, MAC2 = 00 0D 07 00 04 4D, IP 192.168.2x

Enter: adr 0 4 4C 192 168 2 <enter>

This will give the following readback:

Local MAC address 1: 0-d-7-0-4-4c Local MAC address 2: 0-d-7-0-4-4d Local IP address (primary) 192.168.2.x Local IP address (secondary) 192.168.2.x

Type i <enter> to readback the full address including IP byte 4's.

HyperTerminal example – setting & verifying IP & MAC addresses:

adr 7 0 5e 192 168 0 MAC 1 = 00 0D 07 7 0 5E IP 1 = 192.168.0.x MAC 2 = 00 0D 07 7 0 5F IP 2 = 192.168.0.x

Local MAC address 1: 0-d-7-7-0-5e Local MAC address 2: 0-d-7-7-0-5f Local IP address (primary) 192.168.0.50 Local IP address (secondary) 192.168.0.150

Original Calrec file location: S:\Custsupp\Guidance\Ohio\Ohio prog.doc
New SCI file location: Support:SW REVS:Hydra:OHIO prog v4.doc

Last printed 03/02/2014 11:51:00



Programming Software (Ohio_MainApp.bin)

With HyperTerminal connected via RS232, press the box reset.

When the bootloader message appears, press the **b** key on the Hyperterminal PC keyboard to stop the box booting into its application. (<enter> key does not need to be pressed)

Note:

This needs to be done even if the application is not present and the box does not appear to be booting further than the bootloader.

No readback is provided to confirm unit is held in bootloader and no distinctive "kernel style" LED pattern is displayed

Enter the command **NA <enter>** to prepare the card to receive a new application file. This will be displayed as nNaA with echo setting on.

This command takes approximately 30 – 40 seconds to execute, while the current application is being deleted.

Once deleted, you will be prompted to send the new software application file. The card will be generating the "waiting for file transfer" symbols. (symbol type is dependant upon font setting)

Browse to the correct version <code>Ohio_MainApp.bin</code> file from the <code>Transfer>Send File</code> menu.

Ensure protocol is set to Xmodem and send the file.

File transfer takes approximately 1:40 minutes. **Do not reset the box when the file transfer is complete. Wait approximately 10 seconds after the file transfer for the "application file programmed"** message to appear.

Reset the box and wait for the "sending bootup" message, then enter **ver <enter>** to confirm the software and core firmware version.

HyperTerminal example – changing software:

A the broken and broken and a second a second and a second a second and a second an	
Application file programmed	
Please send application .bin file now 3018334	
>NA	
>bnNaA	

** Calrec OHIO Bootloader Rev 1.0 **	



Programming Core Firmware (Chip.rbf)

With HyperTerminal connected via RS232, press the box reset.

When the bootloader message appears, press the **b** key on the Hyperterminal PC keyboard to stop the box booting into its application. (<enter> key does not need to be pressed)

Note:

If the card is still in bootloader from programming software, the firmware file can also be sent without rebooting to bootloader again.

No readback is provided to confirm unit is held in bootloader and no distinctive "kernel style" LED pattern is displayed

Enter the command **NL <enter>** to prepare the card to receive a new logic file. This will be displayed as nNIL with echo setting on.

This command takes approximately 10 seconds to execute, while the current logic file is being deleted.

Once deleted, you will be prompted to send the new logic file. The card will be generating "waiting for file transfer" symbols.

Browse to the correct version **chip.rbf** file from the **Transfer>Send File** menu.

Ensure protocol is set to Xmodem and send the file.

File transfer takes approximately 2.5 minutes. Do not reset the box when the transfer is complete. Wait approximately 35 seconds for the "logic file programmed" message to appear.

Reset the box and wait for the "sending bootup" message, then enter **ver <enter>** to confirm the software and core firmware version.

HyperTerminal example – changing core firmware:

** Calrec OHIO Bootloader Rev 1.0 **	

>bnNlL	
>NL	
Please send logic .rbf file now 3018334	
Logic file programmed	
>	

Original Calrec file location: S:\Custsupp\Guidance\Ohio\Ohio prog.doc

New SCI file location: Support:SW REVS:Hydra:OHIO prog v4.doc

Last printed 03/02/2014 11:51:00



On board firmware programming notes

SU5611 (main PCB within Ohio box) firmware is programmed using Quartus & bytelblaster2. V1.2 (fixes cold boot problem) is currently provided as a .pof file only.

Programming this device erases the MAC & IP addresses. The unit will still readback the correct MAC & IP but the data will be lost after a reset or power cycle. Therefore it is very important to reprogram the addresses after programming this device and to verify the addresses after a reset.

Program as follows:

Connect programming pod and use the auto-detect function of the Quartus programmer to establish the device chain. Two devices should be detected. Select by clicking & highlighting the 570 device (EPM570T100) line. (The chain also shows sub-entries of CFM & UFM under the 570. Only highlight the main line for the 570) Select the **change file** function and browse to the correct programming file, e.g. SU5611_1v1.pof. Select the check boxes for Program/Configure and Verify for this device's main entry line (not CFM/UFM lines). Program & verify as normal for Quartus.